



Ref: FAQ0264

Version: 1.0


Title-Radwin Database-change cal values

Made By: AB 21/09/15


(Issue 2)

How to permanently change or correct logger channel calibration values for incoming data to Radwin software

Open Radwin View, Open the Data File, select the logger you want to change and right click on the logger, then select 'Location Database', then 'Edit location' -



You should see this for the logger -





Ref: FAQ0264

Version: 1.0

Title-Radwin Database-change cal values

Made By: AB 21/09/15

(Issue 2)

Then select the transducer tab and make changes to the settings as required. Note once changes are made the incoming data downloaded from the logger and stored in the database will be to these calibration settings.

Note – if using Datagate and HWM Online then only the Radwin Data is altered – the logger Calibration will be different and Datagate/HWM Online data will not be changed.

Document History:

Edition	Date of Issue	Modification	Notes
1st	02/01/13	Release	
2nd	17/09/15	Format update	